HPCC Systems®

HPCC Data Handling

Boca Raton Documentation Team



HPCC Data Handling

Boca Raton Documentation Team Copyright © 2014 HPCC Systems. All rights reserved

We welcome your comments and feedback about this document via email to <docfeedback@hpccsystems.com> Please include Documentation Feedback in the subject line and reference the document name, page numbers, and current Version Number in the text of the message.

LexisNexis and the Knowledge Burst logo are registered trademarks of Reed Elsevier Properties Inc., used under license. HPCC Systems is a registered trademark of LexisNexis Risk Data Management Inc.

Other products, logos, and services may be trademarks or registered trademarks of their respective companies. All names and example data used in this manual are fictitious. Any similarity to actual persons, living or dead, is purely coincidental.

2014 Version 5.0.0-1

HPCC Data Handling

HPCC Data Handling	4
Introduction	4
Data Handling Terms	5
Working with data files	
Data Handling Methods	9
HPCC Data Backups	15
Introduction	15
Dali data	16
Environment Configuration files	
Thor data files	18
Roxie data files	20
Attribute Repositories	21
Landing Zone files	22

HPCC Data Handling

Introduction

There are a number of different ways in which data may be transferred to, from, or within an HPCC system. For each of these data transfers, there are a few key parameters that must be known.

Prerequisites for most file movements:

- · Logical filename
- · Physical filename
- Record size (fixed)
- · Source directory
- · Destination directory
- Dali IP address (source and/or destination)
- · Landing Zone IP address

The above parameters are used for these major data handling methods:

- Import Spraying Data from the Landing Zone to Thor
- Export Despraying Data from Thor to Landing Zone
- Copy Replicating Data from Thor to Thor (within same Dali File System)
- Copying Data from Thor to Thor (between different Dali File Systems)

Data Handling Terms

A *spray* or *import* is the relocation of a data file from one location (such as a Landing Zone) to a cluster. The term spray was adopted due to the nature of the file movement – the file is partitioned across all nodes within a cluster.

A *despray* or *export* is the relocation of a data file from a cluster to a single machine location (such as a Landing Zone). The term despray was adopted due to the nature of the file movement – the file is reassembled from its parts on all nodes in the cluster and placed in a single file on the destination.

A copy is the replication of a data file from one cluster to another cluster within the same environment.

A Remote copy is the replication of a data file from one cluster to another cluster in a different environment.

A *Landing Zone* (or Drop Zone) is a physical storage location defined in your system's environment. There can be one or more of these locations defined. A daemon (DaFileSrv) must be running on that server to enable file sprays and desprays.

Working with data files

Once you start working with your HPCC system, you will want to process some real data, this section shows you how to load data to your HPCC system.

Before you begin

First, you should consider the size of the data and the capacity of your system. A typical production HPCC system would have much more data capacity than a development system. The size of the files you wish to work with is limited by the size of your system.

Uploading a file

For smaller data files, maximum of 2GB, you can use the upload/download file utility in ECL Watch.


1. In your browser, go to the **ECL Watch** URL displayed example, http://nnn.nnn.nnn.nnn:8010, where nnn.nnn.nnn is your ESP Server's IP address.



Your IP address could be different from the ones provided in the example images. Please use the IP address provided by **your** installation.


2. From ECL Watch page, click on the Upload/download File link in the menu on the left side.

Figure 1. Upload/download



Once you click on the Upload/download file link, it will take you to the dropzones and files page, where you can choose to **Browse** your machine for a file to upload:

Figure 2. Dropzones



3. Press the **Browse** button to browse the files on your local machine, select the file to upload and then click **Open** button.

The file you selected should appear in the **Select a file to upload** field.

4. Press on **Upload Now** to complete the file upload.

Uploading files with a Secure Copy Client

To upload a large file for processing to your virtual machine, you will need a tool that supports the secure copy protocol. In this section, we discuss using WinSCP. There are other tools available, but the steps are similar.


1. Open the WinSCP tool, and login to your Landing Zone node using the username and password given.

Login ID:	hpccdemo
Password:	hpccdemo

2. Once logged in, it should, navigate automatically to the landing zone folder. (/var/lib/LexisNexis/mydropzone)

3. Navigate to where your local file is in the left part of the window.

Figure 3. WinSCP



4. Select the data file to send and copy it to the landing zone, using drag-and-drop.

Data Handling Methods

There are several ways to spray, despray, or copy data files:

- The DFU interface in Ecl Watch
- The DFU Plus command line utility

See the Client Tools manual for details

• Using ECL Code and FileServices library functions.

See the ECL Language Reference for details.

Data Handling Using ECL Watch


• Login to ECL Watch for the environment.

The URL is the IP address where the ESP Server is installed plus the port to which the wssmc service is bound. The default port is 8010. For example:

http://<ESPserverIP>:8010/

• Click on the Files icon, then click on Logical Files.


The Logical Files page displays showing all files with logical entries in the Dali Server's Distributed File System.



From this page, you can despray or copy any file.

Desprays

• Locate the file(s) to despray in the list of files, then Press the the **Despray** action button.



• Provide **Destination** information.

Drop Zone Use the drop list to select the machine to despray to. The items in the list are landing

zones defined in the system's confguration.

Destination-IP Address This is prefilled based upon the selected machine.

Path Provide the complete file path of the destination including file name and extention.

Split Prefix Prefix

Overwrite Check this box to overwrite a file with the same name if it exists.

Use Single Connection Check this box to use a single network connection to despray.

• Press the **Despray** button.

A DFU Workunit tab for each job opens. You can see the progress of each despray operation on the tab. If a job fails, information related to the cause of the failure also displays.

Spray Fixed

- Click on the Files icon, then click the Landing Zones button on the navigation bar.
- Click on the arrow next to your dropzone to expand the list.

The files on your drop zone display.

• Check the checkboxes for the file(s) you want to spray, then click on the **Fixed** link.

The **Spray Fixed** dialog displays.

• Fill in relevant details:

Target

Group Select the name of cluster to spray to. You can only select a cluster in your envi-

ronment.

Name Prefix The prefix for the logical file

Target Name The logical filename to create. This is pre-filled with the name of the source file on

the landing zone, but can be changed.

Record Length The size of each record.

Options:

Overwrite Check this box to overwrite files of the same name.

Replicate Check this box to create backup copies of all file parts in the backup directory (by

convention on the secondary drive of the node following in the cluster).

This option is only available on systems where replication has been enabled.

Compress Check this box to compress the files.

No Split Check this box to prevent splitting file parts to multiple target parts.

Fail if no source file Check this box to allow the spray to fail if no source file is found.

• Press the **Spray** button.

A **DFU Workunit** tab displays for each job. You can see the progress of each despray operation on the tab. If a job fails, information related to the cause of the failure also displays.

Spray Delimited

- Click on the Files icon, then click the Landing Zones button on the navigation bar.
- Click on the arrow next to your dropzone to expand the list.

The files on your drop zone display.

• Check the checkboxes for the file(s) you want to spray, then click on the **Delimited** link.

The **Spray Delimited** page displays.

• Fill in relevant details:

Target

Group Select the name of cluster to spray to. You can only select a cluster in your envi-

ronment.

Name Prefix The prefix for the logical file

Target Name The logical filename to create. This is pre-filled with the name of the source file on

the landing zone, but can be changed.

Options:

HPCC Data Handling HPCC Data Handling

Format Select the format from the droplist

Max Record Length The length of longest record in the file.

Separators The character(s) used as a separator in the source file.

Omit Separator Check this box to omit the separator.

Line Terminators The character(s) used as a line terminators in the source file.

Quote The character used as a quote in the source file.

Overwrite Check this box to overwrite files of the same name.

No Split Check this box to prevent splitting file parts to multiple target parts.

Fail if no source file Check this box to allow the spray to fail if no source file is found.

Replicate Check this box to create backup copies of all file parts in the backup directory (by

convention on the secondary drive of the node following in the cluster).

This option is only available on systems where replication has been enabled.

Compress Check this box to compress the files.

• Press the **Spray** button.

A **DFU Workunit** tab displays for each job. You can see the progress of each despray operation on the tab. If a job fails, information related to the cause of the failure also displays.

Spray XML

- Click on the **Files** icon, then click the Landing Zones button on the navigation bar.
- Click on the arrow next to your dropzone to expand the list.

The files on your drop zone display.

• Check the checkboxes for the file(s) you want to spray, then click on the **Spray XML**hyperlink.

The Spray XML dialog displays.

• Fill in relevant details:

Target

Group Select the name of cluster to spray to. You can only select a cluster in your envi-

ronment.

Name Prefix The prefix for the logical file

Target Name The logical filename to create. This is pre-filled with the name of the source file on

the landing zone, but can be changed.

Options:

Format Select the format from the droplist

Max Record Length The length of longest record in the file.

Overwrite Check this box to overwrite files of the same name.

No Split Check this box to prevent splitting file parts to multiple target parts.

Fail if no source file Check this box to allow the spray to fail if no source file is found.

Replicate Check this box to create backup copies of all file parts in the backup directory (by

convention on the secondary drive of the node following in the cluster).

HPCC Data Handling HPCC Data Handling

This option is only available on systems where replication has been enabled.

Compress Check this box to compress the files.

• Press the **Spray** button.

A **DFU Workunit** tab displays for each job. You can see the progress of each spray operation on the tab. If a job fails, information related to the cause of the failure also displays.

Copy

• Click on the Files icon, then click the Logical Files button on the navigation bar.

• Select the file(s) to copy in the list of files, then click on the **Copy** action button.

• Fill in **Destination** and **Options** information.

Target:

Group Select the name of cluster to copy to. You can only select a cluster in your envi-

ronment.

Target Name The logical filename to create. This is pre-filled with the name of the source file on

the landing zone, but can be changed.

Options:

Replicate Check this box to create backup copies of all file parts in the backup directory (by

convention on the secondary drive of the node following in the cluster).

This option is only available on systems where replication has been enabled.

Wrap Check this box to keep the number of parts the same and wrap if the target cluster

is smaller that the original.

No Split Check this box to prevent splitting file parts to multiple target parts.

Overwrite Check this box to overwrite files of the same name.

Compress Check this box to compress the files.

Retain Superfile Structure Check this box to retain the superfile structure.

• Press the **Copy** button.

A **DFU Workunit** tab displays for each job. You can see the progress of each copy operation on the tab. If a job fails, information related to the cause of the failure also displays.

Remote Copy

Remote Copy allows you to copy data from a cluster outside your environment to one in your environment.

- Click on the **Files** icon, then click the Logical Files button on the navigation bar.
- Click on the Remote Copy link

The Copy File page displays.

• Fill in **Source, Destination,** and **Options** information.

Source:

HPCC Data Handling HPCC Data Handling

Dali The Dali Server in the remote environment

User ID The Username to use to authenticate on the Remote environment

Password The password to use to authenticate on the Remote environment

Logical File The logical filename in the remote environment.

Destination:

Group Select the name of cluster to copy to. You can only select a cluster in your envi-

ronment.

Logical Name The logical name for the copied file.

Options:

Replicate Check this box to create backup copies of all file parts in the backup directory (by

convention on the secondary drive of the node following in the cluster).

This option is only available on systems where replication has been enabled.

Wrap Check this box to keep the number of parts the same and wrap if the target cluster

is smaller that the original.

Overwrite Check this box to overwrite files of the same name.

Compress Check this box to compress the files.

No Split Check this box to prevent splitting file parts to multiple target parts.

Retain Superfile Structure Check this box to retain the superfile structure.

• Press the **Submit** button.

A **DFU Workunit** tab displays. You can see the progress of the copy operation on the tab. If a job fails, information related to the cause of the failure also displays.

 Press the Refresh button periodically until the status of your request indicates it is Finished or click on the View Progress hyperlink to see a progress indicator.

HPCC Data Backups

Introduction

This section covers critical system data that requires regular backup procedures to prevent data loss.

There are

- The System Data Store (Dali data)
- Environment Configuration files
- Data Refinery (Thor) data files
- Rapid Data Delivery Engine (Roxie) data files
- Attribute Repositories
- Landing Zone files

Dali data

The Dali Server data is typically mirrored to its backup node. This location is specified in the environment configuration file using the Configuration Manager.

Since the data is written simultaneously to both nodes, there is no need for a manual backup procedure.

Environment Configuration files

There is only one active environment file, but you may have many alternative configurations.

Configuration manager only works on files in the /etc/HPCCSystems/source/ folder. To make a configuration active, it is copied to /etc/HPCCSystems/environment.xml on all nodes.

Configuration Manager automatically creates backup copies in the /etc/HPCCSystems/source/backup/ folder.

Thor data files

Thor clusters are normally configured to automatically replicate data to a secondary location known as the mirror location. Usually, this is on the second drive of the subsequent node.

If the data is not found at the primary location (for example, due to drive failure or because a node has been swapped out), it looks in the mirror directory to read the data. Any writes go to the primary and then to the mirror. This provides continual redundancy and a quick means to restore a system after a node swap.

A Thor data backup should be performed on a regularly scheduled basis and on-demand after a node swap.

Manual backup

To run a backup manually, follow these steps:

1. Login to the Thor Master node.

If you don't know which node is your Thor Master node, you can look it up using ECL Watch.

2. Run this command:

```
sudo su hpcc
/opt/HPCCSystems/bin/start_backupnode <thor_cluster_name>
```

This starts the backup process.

```
@node219008:~
starting backupnode ...
Using backupnode directory /var/lib/HPCCSystems/hpcc-data/backupnode/last backup
Reading slaves file /var/lib/HPCCSystems/mythor/slaves
Scanning files from dali ...
Waiting for backup to complete
00000000 2012-04-03 14:18:59 23391 23391 "Creating part lists, please wait..."
00000001 2012-04-03 14:18:59 23391 23391 "backupnode: File scan complete, 6 file
s, 5 parts"
00000002 2012-04-03 14:18:59 23391 23391 "backupnode finished"
00000000 2012-04-03 14:19:00 23396 23396 "ssh result(0):
ERR: backupnode: no process killed"
frunssh /var/lib/HPCCSystems/mythor/slaves /bin/sh -c 'mkdir -p /var/log/HPCCSys
tems/backupnode; mkdir -p /var/lib/HPCCSystems/mythor; /opt/HPCCSystems/bin/bac
upnode -T -X /var/lib/HPCCSystems/hpcc-data/backupnode/last_backup %n %c %a %x
> /var/log/HPCCSystems/backupnode/04_03_2012_14_18_59_node*n.log_2>&1' -i:/Users/hpcc/.ssh/id_rsa_-u:hpcc_-pe: -t:0 -a:3 -b
00000000 2012-04-03 14:19:00 23406 23406 "ssh result(0):
00000000 2012-04-03 14:19:05 23454 23454 "10.239.219.8: DONE"
00000001 2012-04-03 14:19:05 23454 23454 "Completed in Om Oc with 0 errors"
 0000002 2012-04-03 14:19:05 23454 23454 "backupnode finished"
[hpcc@oss_development:node219008
```

Wait until completion. It will say "backupnode finished" as shown above.

3. Run the XREF utility in ECL Watch to verify that there are no orphan files or lost files.

Scheduled backup

The easiest way to schedule the backup process is to create a cron job. Cron is a daemon that serves as a task scheduler.

Cron tab (short for CRON TABle) is a text file that contains a the task list. To edit with the default editor, use the command:

sudo crontab -e

Here is a sample cron tab entry:

30 23 * * * /opt/HPCCSystems/bin/start_backupnode mythor

30 represents the minute of the hour.

23 represents the hour of the day

The asterisks (*) represent every day, month, and weekday.

mythor is the clustername

To list the tasks scheduled, use the command:

sudo crontab -1

Roxie data files

Roxie data is protected by three forms of redundancy:

- Original Source Data File Retention: When a query is deployed, the data is typically copied from a Thor cluster's hard drives. Therefore, the Thor data can serve as backup, provided it is not removed or altered on Thor. Thor data is typically retained for a period of time sufficient to serve as a backup copy.
- Peer-Node Redundancy: Each Slave node typically has one or more peer nodes within its cluster. Each peer stores a copy of data files it will read.
- Sibling Cluster Redundancy: Although not required, Roxie deployments may run multiple identically-configured Roxie clusters. When two clusters are deployed for Production each node has an identical twin in terms of data and queries stored on the node in the other cluster.

This provides multiple redundant copies of data files.

Attribute Repositories

Attribute repositories are stored on ECL developer's local hard drives. They can contain a significant number of hours of work and therefore should be regularly backed up. In addition, we suggest using some form of source version control, too.

Landing Zone files

Landing Zones contain raw data for input. They can also contain output files. Depending on the size or complexity of these files, you may want to retain copies for redundancy.